




Windows 7 Firewall – Allow Connection






- 1 – Click on Start
- 2 – Click on Control Panel
- 3 – Click on System and Security
- 4 – Click on Windows Firewall




5 – Click on Advanced Settings

6 – Click on Inbound Rules

7 – Click on New Rule...





8 – Click on Port



Next


9 – TCP needs to be selected

10 – Specific Local Ports – 1022

Next

Next





Next


11 – Name: IP address of Printer

12 – Give the service a Name

Finish

Select Inbound Rule


13 – Click on Properties




11

12

13





14 – Click on Protocols and Ports Tab

15 – Remote Port, Select specific Ports on the drop down, enter 1022

Apply

OK

